

Announcing LinkIQ 1.2 Software

December 16, 2022

Due to a component change in the LinkIQ Cable+Network Tester, a new version – 1.2 – is required. This code will begin shipping in new units in the next few days. It includes no enhancements or bug fixes, and is fully compatible with all existing hardware versions of LinkIQ.

No action is necessary on your part – we just wanted you to be aware of this change. If you want the practice, feel free to upgrade your LinkIQ using the instructions and code found below.

Update your LinkIQ (Optional)

1. Make sure you have backed up any results in your LinkIQ that you want to keep to LinkWare PC.
2. If not installed, download and install the new [LinkWare PC 11](#).
3. Download the new [LinkIQ software](#) to your PC. **(It may be a few days before the code is available.)**
4. Make sure you terminate any VPN running on your PC.
5. Connect your PC to the LinkIQ and start LinkWare PC.
6. Select Utilities > LinkIQ > Software Update. Navigate to the location of the downloaded LinkIQ code and select "Open". The update will start.
7. The LinkIQ will show the progress of the update on the screen, reboot, and be ready to go after a few minutes.

If you have any questions please reach out to Mark Mullins mark.mullins@fluke.com